

## Install Instructions

WARNING: Do not delete these Locations ...\\Root Workspace Location\AZDOT nor the AZDOT-Intl Workspace

WARNING: Do not delete the Location ...\\AZDOT

WARNING: Do not uninstall any existing CONNECT Edition software

Install Versions are shown on the CADD Webpage


<https://azdot.gov/business/engineering-and-construction/cadd>

Download AZDOT\_10.12.zip to C:\temp\

Extract All to C:\ or server drive letter

**AZDOT-2022R3 Workspace shall be used on all new projects**

**NOTE: This update will not damage the existing WorkSpaces**



Extract

C:\AZDOT\_10.12\Configuration\

Edit ConfigurationSetup.cfg

#-----

#-----

# START: The section defines user selection at the time of installation.

# These lines are generated by installer.

[General]

\_USTN\_CUSTOM\_CONFIGURATION = Z:/AZDOT\_10.12/Configuration/

Revise \_USTN\_CUSTOM\_CONFIGURATION = Z:/AZDOT\_10.12/Configuration/  
to C:/AZDOT\_10.12/Configuration/ or server drive letter

\_USTN\_CUSTOM\_CONFIGURATION = C:/AZDOT\_10.12/Configuration/

Save

Copy C:\AZDOT\_10.12\Configuration\ConfigurationSetup.cfg and WorkspaceSetup.cfg to

C:\ProgramData\Bentley\OpenRoads Designer CE 10.12\Configuration\

and

C:\ProgramData\Bentley\OpenBridge Designer CE 10.12.1\OpenBridgeModeler\Configuration\

Browse to

C:\AZDOT\_10.12\Configuration\WorkSpaces\AZDOT-2022R3\WorkSets

For each project

Copy NewProject folder and Paste

Rename to the tracs number

Copy NewProject.cfg and Paste

Rename to tracs number.cfg

Start OpenRoads Designer CE – 2022 Release 3

# OpenRoads Designer CE

WorkSpace

WorkSet


AZDOT-2022R3 ▾ NewProject ▾

## Recent Files

You haven't opened any files recently. To browse for a file, start by clicking on Browse.




Start OpenBridge Designer 2022 Release 2





New File

Select>OpenBridge Modeler


OpenBridge Designer CE 2022 Release 2

  
Modeling

  
Analysis

  
Drawings

Modeling



OpenBridge  
Modeler

File Not Created  
Run application to begin.


## OpenBridge Modeler CE


WorkSpace      WorkSet

AZDOT-2022R3 ▾ NewProject ▾

### Recent Files

You haven't opened any files recently. To browse for a file, start by clicking on Browse.


  
Browse

  
New File


AZDOT\_10.12 (1)

Configuration (2)


Organization-Civil (3)






WorkSpaces (3)











WorkSets (4)



dgn (5)

-  dgn
-  out
-  Standards

Group folder (6)

-  Bridge
-  Drainage
-  Roadside
-  Roadway
-  Seed
-  Survey
-  Traffic
-  Utilities